

Combinatorial Optimization in Computer Vision (IN2245)

Frank R. Schmidt
Csaba Domokos

Winter Semester 2015/2016

20. Fast Trust Region	2
Trust Region	3
Continuous Functions	4
Taylor Approximations	5
Approximation Reliability	6
Trust Region Method	7
Trust Region Parameters	8
First Order Trust Region	9
Second Order Trust Region	10
Summary and Outlook: Trust Region	11
Shape Distances	12
Trust Region of Segmentations	13
Hamming Distance	14
Modular Distances	15
Quadratic Pseudo-Boolean Optimization	16
Local Submodular Approx. of QPBO	17

Combinatorial Constrained Optimization	18
Fast Trust Region Method	19
Segmentation with Repulsion	20
Image Segmentation with Repulsion	21
Regional Functions	22
Outlook: Regional Functions	23
Literature *	24

Continuous Functions

The **trust region framework** is a popular framework for **continuous energy minimization**. After revising it, we will see how it can be adapted for **combinatorial optimization**.

In the continuous setup, we assume that a smooth function $f: \mathbb{R}^n \rightarrow \mathbb{R}$ is given, *i.e.*, f and all its derivatives are continuous and themselves differentiable.

The general derivatives turn out to be high-order tensors. For that reason, we will focus just on the 1st and 2nd order derivatives.

The **gradient** ∇f and the **Hesse matrix** Hf (cf. **Analysis I/II**) are mappings

$$\nabla f: \mathbb{R}^n \rightarrow \mathbb{R}^n$$

$$Hf: \mathbb{R}^n \rightarrow \mathbb{R}^{n \times n}.$$

Taylor Approximations

Given a specific point $x_0 \in \mathbb{R}^n$, we can define the Taylor sequence (cf. **Analysis I / II**). Of practical use are the 1st and 2nd order **Taylor approximations**

$$\begin{aligned} T_{x_0}^1 f(x) &= f(x_0) + \langle \nabla f(x_0), x - x_0 \rangle \\ T_{x_0}^2 f(x) &= f(x_0) + \langle \nabla f(x_0), x - x_0 \rangle \\ &\quad + \frac{1}{2} \langle Hf(x_0) \cdot (x - x_0), x - x_0 \rangle. \end{aligned}$$

Since the minimization of linear and quadratic functions is easy to perform, most local minimization approaches focus on the linear Taylor approximation $T^1 f$ or the quadratic Taylor approximation $T^2 f$.

Approximation Reliability

All Taylor approximations are accurate for $x = x_0$, but the further we move away from this **development point** x_0 , the less reliable the approximation becomes.

Thus, we want to define a **region** around x_0 in which we **trust** a specific approximation. This region can be defined by a single parameter, its distance $d \in \mathbb{R}^+$ from the development point x_0 , *i.e.*,

$$B_d(x_0) := \{x \in \mathbb{R}^n \mid \|x - x_0\| \leq d\}$$

During the **trust region optimization**, we will adapt this distance d . It is therefore not a global parameter, but a parameter that changes due to the local behavior of the function f .

Trust Region Method

Let us assume that we have an energy $f: \mathbb{R}^n \rightarrow \mathbb{R}$ and for each $x_0 \in \mathbb{R}^n$ an approximative energy $\tilde{f}_{x_0}: \mathbb{R}^n \rightarrow \mathbb{R}$ such that $\tilde{f}_{x_0}(x_0) = f(x_0)$. Then, the trust region method works as follows:

1. Let $x_0 \in \mathbb{R}^n$ be an arbitrary initial solution and $d > 0$ be an arbitrary initial distance that defines the trust region $B_d(x_0)$ around x_0 .
2. Let x^* be a global optimum of the **trust region subproblem**:

$$\min_{x \in B_d(x_0)} \tilde{f}_{x_0}(x)$$

3. Set $\rho := \frac{f(x_0) - f(x^*)}{\tilde{f}_{x_0}(x_0) - \tilde{f}_{x_0}(x^*)}$.
4. If $\rho > \tau_1$, set $x_0 := x^*$.
5. If $\rho > \tau_2$, set $d := d \cdot \alpha$, otherwise $d := d/\alpha$.
6. If not converged, go to Step 2.

Trust Region Parameters

There are three different design parameters for the trust region method, namely $0 < \tau_1 < \tau_2 < 1$ and $\alpha > 1$.

The α -parameter describes how the trust region changes during the method. It is common to use $\alpha = 2$.

The τ_1 -parameter controls when to accept x^* as a good candidate. In the continuous framework, $\tau_1 > 0$ has to be chosen in order to guarantee convergence. In the combinatorial framework, we can also use $\tau_1 = 0$, but this may result in a higher running time.

The τ_2 -parameter controls when to expand or shrink the trust region.

A common choice is $\tau_2 = 0.25$.

First Order Trust Region

If we use $T_{x_0}^1 f$ as the approximative energy \tilde{f}_{x_0} , the trust region subproblem

$$\min_{\|x-x_0\| \leq d} f(x_0) + \langle \nabla f(x_0), x - x_0 \rangle$$

is uniquely minimized by

$$x^* = x_0 - d \cdot \frac{\nabla f(x_0)}{\|\nabla f(x_0)\|}$$

In the case of the first order Taylor approximation, the trust region method is a **gradient descent** variant.

It is called the **normalized gradient descent method**.

Second Order Trust Region

If we use $T_{x_0}^2 f$ as the approximative energy \tilde{f}_{x_0} , the trust region subproblem

$$\min_{\|x-x_0\| \leq d} f(x_0) + \langle \nabla f(x_0), x - x_0 \rangle + \frac{1}{2} \langle Hf(x_0)(x - x_0), x - x_0 \rangle$$

is uniquely minimized by $x^* \in B_d(x_0)$. This method is called the **trust region Newton method**.

For big d , we obtain

$$x^* = x_0 - Hf(x_0)^{-1}(\nabla f(x_0)),$$

which is the **Newton iteration**.

Summary and Outlook: Trust Region

The trust region framework can be seen as a generalization of different, continuous optimization techniques.

In particular, it includes the *normalized gradient descent approach* and the *trust region Newton method*.

Nonetheless, it is not restricted to continuous energy minimization. In fact, it can be easily extended to arbitrary combinatorial problems.

In order to do this, we have to make specific decisions: Firstly, we have to define the approximation \tilde{E} of function E given a specific discrete solution S_0 .

Secondly, we have to define a trust region with respect to S_0 .

Thirdly, we have to find the global optimum of \tilde{E} within the trust region.

Trust Region of Segmentations


Given a specific segmentation $S_0 \subset \Omega$, we want to define a region $B_d(S_0) \subset \mathcal{P}(\Omega)$ of segmentations for which we like to trust an approximation \tilde{E} of an energy E .

This can be done by introducing a positive definite distance function $\text{dist}: \mathcal{P}(\Omega) \times \mathcal{P}(\Omega) \rightarrow \mathbb{R}_0^+$ on the set $\mathcal{P}(\Omega)$ of possible segmentations.

A commonly used distance between sets is the **Hamming distance**:


$$\begin{aligned}\text{dist}_H(S, T) &= \text{area}(S \Delta T) \\ &= \int_{S \setminus T} 1 \, dx + \int_{T \setminus S} 1 \, dx \\ &= \int_{S - (S \cap T)} 1 \, dx + \int_{T - (S \cap T)} 1 \, dx\end{aligned}$$

Hamming Distance



$$\begin{aligned}\text{dist}_H(S, T) &= \int_{T-(S \cap T)} 1 dx + \int_{S-(S \cap T)} 1 dx \\ &= \int_{T-(S \cap T)} \phi_S dx - \int_{S-(S \cap T)} \phi_S dx \\ &= \int_T \phi_S dx - \int_S \phi_S dx\end{aligned}$$

Modular Distances



The Hamming distance $\text{dist}_H(S, T)$ is modular in T and can therefore be easily optimized. Similarly, we can define different modular distance function like dist_2 that is driven by the signed distance function.

$$\text{dist}_H(S, T) = \int_T \phi_S(x) dx - \int_S \phi_S(x) dx$$

$$\text{dist}_2(S, T) = \int_T \text{sdf}_{S_0}(x) dx - \int_S \text{sdf}_S(x) dx$$

Local Submodular Approx. of QPBO

Given a quadratic pseudo-Boolean function $E: \mathbb{B}^n \rightarrow \mathbb{R}$

$$E(x) = C + \sum_{i=1}^n f_i x_i + \sum_{\substack{i,j=1 \\ f_{i,j} < 0}}^n f_{i,j} x_i x_j + \sum_{\substack{i,j=1 \\ f_{i,j} > 0}}^n f_{i,j} x_i x_j$$

and an initial segmentation $x^{(0)} \in \mathbb{B}^n$, we define the following submodular approximation of E :

$$\tilde{E}(x) = C + \sum_{i=1}^n f_i x_i + \sum_{\substack{i,j=1 \\ f_{i,j} < 0}}^n f_{i,j} x_i x_j + \sum_{\substack{i,j=1 \\ f_{i,j} > 0}}^n f_{i,j} x_i^{(0)} x_j + f_{i,j} x_i x_j^{(0)}$$

This approximation only computes the first order Taylor approximation for the supermodular term. It is therefore a submodular (not a linear) approximation.

Combinatorial Constrained Optimization

Given the submodular energy \tilde{E} , we like to solve

$$\min_{\text{dist}(x_0, x) \leq d} \tilde{E}(x). \quad (1)$$

We can relax this problem by minimizing

$$\tilde{E}(x) + \lambda \cdot \text{dist}(x_0, x) \quad (2)$$

instead.

Note that $\lambda = 0$ ($\lambda = \infty$) in (2) leads to the same solution as $d = \infty$ ($d = 0$) in (1). Thus, we can assume a relationship of $d \approx \frac{1}{\lambda}$.

This leads to a different method, that we called **Fast Trust Region**.

Fast Trust Region Method

Let us assume that we have an energy $E: \mathbb{B}^n \rightarrow \mathbb{R}$ and for each $x_0 \in \mathbb{B}^n$ an approximative energy $\tilde{E}_{x_0}: \mathbb{B}^n \rightarrow \mathbb{R}$ such that $\tilde{E}_{x_0}(x_0) = E(x_0)$. Then, the fast trust region method works as follows:

1. Let $x_0 \in \mathbb{B}^n$ be an arbitrary initial solution and $\lambda > 0$.
2. Let x^* be a global optimum of the **fast trust region subproblem**:

$$\min_{x \in \mathbb{B}^n} \tilde{E}_{x_0}(x) + \lambda \cdot \text{dist}(x_0, x)$$

3. Set $\rho := \frac{E(x_0) - E(x^*)}{\tilde{E}_{x_0}(x_0) - \tilde{E}_{x_0}(x^*)}$.
4. If $\rho > \tau_1$, set $x_0 := x^*$.
5. If $\rho > \tau_2$, set $\lambda := \lambda/\alpha$, otherwise $\lambda := \lambda \cdot \alpha$.
6. If not converged, go to Step 2.

In practice, we choose $\tau_1 = 0$, $\tau_2 = 0.25$ and $\alpha = 2$.

Segmentation with Repulsion

The classical image segmentation framework combines a **data term** with a **length term**


$$E(x) = \sum_{i=1}^n f_i x_i + \sum_{i=1}^n \sum_{j \in \mathcal{N}(i)} f_{ij} x_i x_j \quad f_{ij} \leq 0.$$

The length term can also be seen as an **attraction force**, since label clusters attract each other. In other words, it is cheaper to combine two clusters into one cluster if they are close to one another.

If we want to model a **repulsion force**, we need to use supermodular terms:

$$f_{ij} = \frac{|I(i) - I(j)| - c}{\text{dist}(i, j)}$$

Image Segmentation with Repulsion



Image



Graph Cut
(without Repulsion)



QPBO



TRWS



FTR

Outlook: Regional Functions

In the next lecture we will address a special class of **higher-order pseudo-Boolean energies**

$$E(S) = E_0(S) + R_{\{f_i\}_{i < k}}^F(S)$$

- E_0 is a submodular function
- $R_{\{f_i\}_{i < k}}^F$ is a **regional function**, i.e.,

$$R_{\{f_i\}_{i < k}}^F(S) = F(\langle f_0, S \rangle, \dots, \langle f_{k-1}, S \rangle)$$

where

$$f_i : \Omega \rightarrow \mathbb{R}$$

“indicator” function

$$F : \mathbb{R}^k \rightarrow \mathbb{R}$$

smooth composition

Literature *

Trust Region

- Levenberg, *A Method for the Solution of Certain Non-Linear Problems in Least Squares*, 1944, Quarterly of Applied Mathematics 2, 164–168.
- Marquardt, *An Algorithm for Least-Squares Estimation of Nonlinear Parameters*, 1963, SIAM J. on Applied Mathematics 11(2), 431–441.
- Sorenson, *Newton's Method with a Model Trust Region Modification*, 1987, SIAM J. Numerical Analysis 24, 1152–1170.

Fast Trust Region in Computer Vision

- Gorelick, Schmidt, Boykov, DeLong, Ward. *Segmentation with non-linear regional constraints via line-search cuts*, 2012, ECCV, 583–597.
- Gorelick, Schmidt, Boykov. *Fast Trust Region for Segmentation*, 2013, IEEE CVPR.
- Gorelick, Boykov, Veksler, Ben Ayed, DeLong. *Submodularization for Binary Pairwise Energies*, 2014, IEEE CVPR.